



*PROPRIETARY
INFORMATION*

ORBIT READER 20

***Protocol to communicate with screen
readers v0.0***

**23rd September, 2017
Version 0.0**

Revision History

Rev.	Date	Description of Changes	Author
0.0	23-Sep-17	Created	

1 Contents

1	CONTENTS	3
2	SERIAL/BLEETOOTH PROTOCOL	4
2.1	TRANSFER-DIRECTION: PC ⇒ OR20 (OUT REPORTS)	4
2.1.1	\$01 Display-data	4
2.1.2	\$05 Call major firmware version-number	4
2.1.3	\$08 Repeat all	4
2.1.4	\$15 Protocol on/off	4
2.1.5	\$16 Get Communication Channel	5
2.1.6	\$84 Call Device ID	5
2.1.7	\$8A Call Serial-Number	5
2.1.8	\$8C Call Bluetooth Device Name	5
2.2	TRANSFER-DIRECTION: OR20 ⇒ PC (IN REPORTS)	6
2.2.1	\$01 Number of cells	6
2.2.2	\$15 Protocol on/off	6
2.2.3	\$16 Communication-Channel USB, HID or BT	6
2.2.4	\$24 Button-data	6
2.2.5	\$33 Braille Keys	6
2.2.6	\$34 Arrow Keys	7
2.2.7	\$84 Device ID	7
2.2.8	\$8A Serial Number	8
2.2.9	\$8C Bluetooth Device Name	8
3	HID PROTOCOL	9
3.1	TRANSFER-DIRECTION: PC ⇒ OR20 (OUT REPORTS)	9
3.1.1	\$01 Display-data	9
3.1.2	\$05 Call major firmware version-number	9
3.1.3	\$02 Info request	9
3.1.4	\$08 Repeat all	9
3.1.5	\$15 Protocol on/off	9
3.1.6	\$16 Get Communication Channel	10
3.1.7	\$84 Call Device ID	10
3.1.8	\$8A Call Serial-Number	10
3.1.9	\$8C Call Bluetooth Device Name	10
3.2	TRANSFER-DIRECTION: OR20 ⇒ PC (IN REPORTS)	11
3.2.1	\$01 Number of cells	11
3.2.2	\$05 Major Version number	11
3.2.3	\$15 Protocol on/off	11
3.2.4	\$16 Communication-Channel USB, HID or BT	11
3.2.5	\$24 Button-data	11
3.2.6	\$33 Braille Keys	11
3.2.7	\$34 Arrow Keys	12
3.2.8	\$84 Device ID	12
3.2.9	\$8A Serial Number	13
3.2.10	\$8C Bluetooth Device Name	13
4	CONFIGURATION TABLE	13

2 Serial/Bluetooth Protocol

<Esc> (= \$1B) shows the beginning of an information-block. If there is an <ESC> between the data, it will be sent twice and reduced to one at the receiver. We've defined the following infotypes at the Escape-Protocol for the communication with the APH device:

2.1 Transfer-direction: PC ⇒ OR20 (Out reports)

2.1.1 \$01 Display-data

This report is used to display something on the Braille display.

ESC
\$01
Byte 0
Byte 1
Byte 2
...
...
Byte 19

Position of the display-elements:

0	19

2.1.2 \$05 Call major firmware version-number

This infotype is used to receive the major firmware version from the device. To get full version number please check \$85 infotype.

ESC
\$05

2.1.3 \$08 Repeat all

This report is used to receive all buttons status (button is pressed/not pressed).

ESC
\$08

2.1.4 \$15 Protocol on/off

If the protocol is turned on, the device enters in communication mode and sends the device ID, the serial number and the Braille display length.

ESC	
\$15	
Data	0 = Off / 1 = On

2.1.5 \$16 Get Communication Channel

This report is used to get the current communication channel. Data must be \$FF to receive the current channel.

ESC	
\$16	
Data	\$FF – query for the current setting

2.1.6 \$84 Call Device ID

This report calls the device-ID.

ESC
\$84

2.1.7 \$8A Call Serial-Number

This report calls the serial number of the device.

ESC
\$8A

2.1.8 \$8C Call Bluetooth Device Name

This report calls the Bluetooth Device Name.

ESC
\$8C

2.2 Transfer-direction: OR20 ⇒ PC (IN Reports)

2.2.1 \$01 Number of cells

No matter if more or less data is received this will trigger the \$01 (Number of cells) report.

ESC	
\$01	
Number of cells	20

2.2.2 \$15 Protocol on/off

If the protocol is turned on, the device enters in communication mode and sends the device ID, the serial number and the Braille display length.

ESC	
\$15	
Data	0 = Off / 1 = On

2.2.3 \$16 Communication-Channel USB, HID or BT

This report will be sent if the report parameter received from PC is \$FF.

ESC	
\$16	
Data	\$00 – USB \$01 – Bluetooth \$03 – HID

2.2.4 \$24 Button-data

ESC
\$24
Byte

	bit7	bit6	bit5	Bit4	bit3	bit2	bit1	bit0
Byte	0	0	D6	PR OR D5	D4	D3	PL or D2	D1

PL = Panning Left

PR = Panning Right

Pressing the “Select” key first and then the B1... B6 keys the device will emulate the D1...D6 keys.

2.2.5 \$33 Braille Keys

ESC
\$33
Byte1
Byte2

	Bit 7	Bit 6	Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0
Byte1	0	0	0	0	0	0	0	B9
Byte2	B8	B7	B6	B5	B4	B3	B2	B1

Position of Braille Keys

B3 – B2 – B1		B4 – B5 – B6
B7	B9	B8

2.2.6 \$34 Arrow Keys

ESC
\$34
Byte

\

	Bit 7	Bit 6	Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0
Byte	0	0	0	Select	Right	Down	Left	Up

Position of Joystick keys

	Up	
Left	Select	Right
	Down	

2.2.7 \$84 Device ID

This report is sent once, if the communication protocol is started. It is also sent, as an answer to the report \$84 (Call Device-ID). The 16 bytes following the infotype represent the Device-ID in ASCII. If the name has less than 16 characters it will be filled with 0(ASCII 0 character). For example Device-ID is: “**Orbit Reader 20**”.

ESC	Device name as 16 ASCII bytes (padded with 0 at the end for the unused characters)
\$84	
Byte 1	
Byte 2	
Byte 3	
Byte 4	
Byte 5	
Byte 6	
Byte 7	
Byte 8	
Byte 9	
Byte 10	
Byte 11	
Byte 12	
Byte 13	
Byte 14	
Byte 15	
Byte 16	

2.2.8 \$8A Serial Number

This report is sent once, if the protocol is started. It is also sent if infotype \$8A (Call Serial Number) received. The 8 bytes following the infotype are the serial number as 8 ASCII characters.

ESC
\$8A
Byte1
Byte2
...
Byte7
Byte8

2.2.9 \$8C Bluetooth Device Name

This report sends the Device Bluetooth Name. The name will be padded with 0 at the end for the unused characters.

ESC	Infotype
\$8C	
ASCII 1	Bluetooth device name as 20 ASCII bytes (padded with 0 at the end for the unused characters)
ASCII 2	
.	
.	
.	
.	
ASCII 13	
ASCII 14	

3 HID Protocol

The communication between the device and PC is made using IN/OUT reports.

3.1 Transfer-direction: PC \Rightarrow OR20 (Out reports)

3.1.1 \$01 Display-data

This report is used to display something on the Braille display.

\$01
Byte 0
Byte 1
Byte 2
...
...
Byte 19

Position of the display-elements:

0	19

3.1.2 \$05 Call major firmware version-number

This infotype is used to receive the major firmware version from the device. To get full version number please check \$85 infotype. Version number 255 is send by all beta versions

\$05
Any value

3.1.3 \$02 Info request

This report is used to get the device information. The reports \$84, \$8A and \$01 will be received.

\$02
Value 0

3.1.4 \$08 Repeat all

This report is used to receive all buttons status (button is pressed/not pressed).

\$08
Any value

3.1.5 \$15 Protocol on/off

If the protocol is turned on, the device enters in communication mode and sends the device ID, the serial number and the Braille display length.

\$15	
Data	0 = Off / 1 = On

3.1.6 \$16 Get Communication Channel

This report is used to get the current communication channel. Data must be \$FF to receive the current channel.

\$16	
Data	\$FF – query for the current setting

3.1.7 \$84 Call Device ID

This report calls the device-ID.

\$84
Any value

3.1.8 \$8A Call Serial-Number

This report calls the serial number of the device.

\$8A
Any value

3.1.9 \$8C Call Bluetooth Device Name

This report calls the Bluetooth Device Name.

\$8C
Any value

3.2 Transfer-direction: OR20 ⇒ PC (IN Reports)

3.2.1 \$01 Number of cells

No matter if more or less data is received this will trigger the \$01 (Number of cells) report.

\$01	
Number of cells	"N"

3.2.2 \$05 Major Version number

\$05
Major Version

3.2.3 \$15 Protocol on/off

If the protocol is turned on, the device enters in communication mode and sends the device ID, the serial number and the Braille display length.

\$15	
Data	0 = Off / 1 = On

3.2.4 \$16 Communication-Channel USB, HID or BT

This report will be sent if the report parameter received from PC is \$FF.

\$16	
Data	\$00 – USB \$01 – Bluetooth \$03 – HID

3.2.5 \$24 Button-data

\$24
Byte

	bit7	bit6	bit5	Bit4	bit3	bit2	bit1	bit0
Byte	0	0	D6	PR OR D5	D4	D3	PL or D2	D1

PL = Panning Left

PR = Panning Right

Pressing the "Select" key first and then the B1... B6 keys the device will emulate the D1...D6 keys.

3.2.6 \$33 Braille Keys

\$33
Byte1
Byte2

	Bit 7	Bit 6		Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0
Byte1	0	0		0	0	0	0	0	B9
Byte2	B8	B7		B6	B5	B4	B3	B2	B1

Position of Braille Keys

B3 – B2 – B1		B4 – B5 – B6
B7	B9	B8

3.2.7 \$34 Arrow Keys

\$34
Byte

	Bit 7	Bit 6	Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0
Byte	0	0	0	Select	Right	Down	Left	Up

Position of Joystick keys

	Up	
Left	Select	Right
	Down	

3.2.8 \$84 Device ID

This report is sent once, if the communication protocol is started. It is also sent, as an answer to the report \$84 (Call Device-ID). The 16 bytes following the infotype represent the Device-ID in ASCII. If the name has less than 16 characters it will be filled with 0(ASCII 0 character). For example, Device-ID is: “**Orbit Reader 20**”.

\$84	Device name as 16 ASCII bytes (padded with 0 at the end for the unused characters)
Byte 1	
Byte 2	
Byte 3	
Byte 4	
Byte 5	
Byte 6	
Byte 7	
Byte 8	
Byte 9	
Byte 10	
Byte 11	
Byte 12	
Byte 13	
Byte 14	
Byte 15	
Byte 16	

3.2.9 \$8A Serial Number

This report is sent once, if the protocol is started. It is also sent if infotype \$8A (Call Serial Number) received. The 8 bytes following the infotype are the serial number as 8 ASCII characters.

\$8A
Byte1
Byte2
...
Byte7
Byte8

3.2.10 \$8C Bluetooth Device Name

This report sends the Device Bluetooth Name. The name will be padded with 0 at the end for the unused characters.

\$8C	Infotype
ASCII 1	Bluetooth device name as 20 ASCII bytes (padded with 0 at the end for the unused characters)
ASCII 2	
.	
.	
.	
.	
ASCII 13	
ASCII 14	

4 Configuration table

#	Field	Value
1	Product Name	"Orbit Reader 20 "(Please make note of the trailing space after '20' ".
2	USB Vendor ID (VID) (For both USB serial and USB HID)	0x0483
3	USB Product ID (PID) for HID mode	0xA1D3
5	USB Product ID (PID) for serial mode	0x5740
5	Bluetooth Name	Orbit reader 20 xxxx (xxxx is the last four digits of the unit serial number and so it varies from unit to unit)
6	Size of the display	20 cell
7	Communication modes supported	USB HID, USB Serial, Bluetooth (SPP profile)